

# erwin Data Intelligence Suite

Life Cycle Management Guide

Release v10.1

### **Legal Notices**

This Documentation, which includes embedded help systems and electronically distributed materials (hereinafter referred to as the "Documentation"), is for your informational purposes only and is subject to change or withdrawal by erwin Inc. at any time. This Documentation is proprietary information of erwin Inc. and may not be copied, transferred, reproduced, disclosed, modified or duplicated, in whole or in part, without the prior written consent of erwin Inc.

If you are a licensed user of the software product(s) addressed in the Documentation, you may print or otherwise make available a reasonable number of copies of the Documentation for internal use by you and your employees in connection with that software, provided that all erwin Inc. copyright notices and legends are affixed to each reproduced copy.

The right to print or otherwise make available copies of the Documentation is limited to the period during which the applicable license for such software remains in full force and effect. Should the license terminate for any reason, it is your responsibility to certify in writing to erwin Inc. that all copies and partial copies of the Documentation have been returned to erwin Inc. or destroyed.

TO THE EXTENT PERMITTED BY APPLICABLE LAW, ERWIN INC. PROVIDES THIS DOCUMENTATION "AS IS" WITHOUT WARRANTY OF ANY KIND, INCLUDING WITHOUT LIMITATION, ANY IMPLIED WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE, OR NONINFRINGEMENT. IN NO EVENT WILL ERWIN INC. BE LIABLE TO YOU OR ANY THIRD PARTY FOR ANY LOSS OR DAMAGE, DIRECT OR INDIRECT, FROM THE USE OF THIS DOCUMENTATION, INCLUDING WITHOUT LIMITATION, LOST PROFITS, LOST INVESTMENT, BUSINESS INTERRUPTION, GOODWILL, OR LOST DATA, EVEN IF ERWIN INC. IS EXPRESSLY ADVISED IN ADVANCE OF THE POSSIBILITY OF SUCH LOSS OR DAMAGE.

The use of any software product referenced in the Documentation is governed by the applicable license agreement and such license agreement is not modified in any way by the terms of this notice.

The manufacturer of this Documentation is erwin Inc.

Provided with "Restricted Rights." Use, duplication or disclosure by the United States Government is subject to the restrictions set forth in FAR Sections 12.212, 52.227-14, and 52.227-19 (c)(1) - (2) and DFARS Section 252.227-7014(b)(3), as applicable, or their successors.

Copyright © 2020 erwin Inc. All rights reserved. All trademarks, trade names, service marks, and logos referenced herein belong to their respective companies.

### **Contact erwin**

#### **Understanding your Support**

Review support maintenance programs and offerings.

#### **Registering for Support**

Access the erwin support site and click Sign in to register for product support.

#### **Accessing Technical Support**

For your convenience, erwin provides easy access to "One Stop" support for <u>erwin Data Intelligence Suite</u> (DI Suite), and includes the following:

- Online and telephone contact information for technical assistance and customer services
- Information about user communities and forums
- Product and documentation downloads
- erwin Support policies and guidelines
- Other helpful resources appropriate for your product

For information about other erwin products, visit http://erwin.com/.

#### **Provide Feedback**

If you have comments or questions, or feedback about erwin product documentation, you can send a message to distechpubs@erwin.com.

#### erwin Data Modeler News and Events

Visit <u>www.erwin.com</u> to get up-to-date news, announcements, and events. View video demos and read up on customer success stories and articles by industry experts.

# **Contents**

| Legal Notices2                           |
|--|
| Contents                                 |
| Managing Life Cycles                     |
| Using Requirements Manager               |
| Creating Projects 8                      |
| Configure Users10                        |
| Managing Projects                        |
| Creating Specifications                  |
| Documenting Requirements                 |
| Adding Supporting Documents              |
| Setting up Collaborations                |
| Managing Collaborations                  |
| Creating Child Artifacts 25              |
| Managing Specifications 28               |
| Creating Specification Versions          |
| Exporting and Importing Specifications   |
| Linking Requirements to Data Mappings    |
| Using Test Manager                       |
| Creating and Managing Test Cases         |
| Viewing and Analyzing Test Cases         |
| Using Release Manager                    |
| Creating Projects and Adding Releases 45 |

| Adding Release Objects to Releases           | 50 |
|--|----|
| Adding Data Item Mappings as Release Objects | 50 |
| Promoting Data Item Mappings                 | 57 |
| Adding Codeset as Release Objects            | 62 |
| Adding Code Mappings as Release Objects      | 67 |
| Adding Miscellaneous Objects                 | 72 |
| Moving Release Objects                       | 76 |
| Sorting Projects and Releases                | 78 |

### **Managing Life Cycles**


This section walks you through life cycle management in a data integration project. It involves requirements, release, and test management.

- Requirements management is done via Requirements Manager. It involves standardizing functional requirements documentation, creating, collaborating, and customizing templates to manage functional requirements, and linking requirements to data mappings.
- Test management is done via Test Manager. It involves viewing and analyzing test specifications created under Metadata Manager and Mapping Manager.
- Release management is done via Release Manager. It involves creating and managing releases and release calendars. You can release data mappings, database objects, and release notes to standardize the release process.

### **Using Requirements Manager**

To access the Requirements Manager, go to **Application Menu > Data Catalog > Requirements Manager**.

The Requirements Manager dashboard appears:



| UI Section     | Function  |
|----------------|---|
| 1-Requirements | Use this pane to browse through projects and specifications. It enables you |
| Workspace      | to categorize and create specifications under projects.                     |
| 2-Right Pane   | Use this pane to view or work on the data based on your selection in the    |
|                | Requirements Workspace.   |
| 3-Summary      | Use this pane to view a summary of projects.                                |

Managing requirements involves the following:


- Creating and managing projects
- Creating and managing specifications
- Linking the requirements to mappings

## **Creating Projects**

Projects are collections of your functional specifications and requirements. To define functional specifications, you can use the <u>templates</u> that were created under Requirements Manager settings. You can group these specifications under subjects.


To create projects, follow these steps:

- 1. Go to Application Menu > Data Catalog > Requirements Manager.
- 2. In the **Requirements Workspace** pane, right-click the **Specification Templates Catalogue** node.



3. Click Create Project.

The Create Project page appears.



4. Enter Project Name and Project Description.

For example:

- Project Name: Nasdag PDLC
- Project Description: This project captures functional and business requirements of the data migration project
- 5. Click

The project is created and added under Specification Templates Catalogue.

**Note**: You can also create subjects under projects to group specifications by their functions.

Once a project is created you can:

- Configure users
- Create specifications

Right-click or select a project in the Requirements Workspace pane to manage it. Managing projects involves:

- Creating subjects
- Editing or deleting projects
- Viewing project specifications


### **Configure Users**

Once you have created a project, you can configure users to access and work on the project. These users will have Write access to all subjects and specifications under a project.

To configure users, follow these steps:

1. In the **Requirements Workspace** pane, select a project.

The following page appears.




2. Click the Project Users tab.



3. Click Configure Users.

The Assign/Unassign Users page appears.



- 4. Select one or more users to assign them to the project.
- 5. Click

The selected users are assigned to the project.


## **Managing Projects**

Managing projects involves:

- Creating subjects
- Editing or deleting projects
- Viewing project specifications

To manage project, follow these steps:

1. Right-click a project to view project management options.



2. Use the following options:

#### **New Subject**

Use this option to create new subjects. Subjects let you group specifications logically.

#### **Edit Project**


Use this option to update project name and its description. Alternatively, you can follow these steps:

- 1. In the Requirements Workspace pane, select a project.
- 2. Click the Project Details tab.
- 3. Click .

#### **Delete Project**

Use this option to delete the project.

To view a list of project specifications, in the Requirements Workspace pane, select a project. The list of specifications under the project appears on the Specifications Details tab.




### **Creating Specifications**

Under each requirements project, you can add functional specifications that define the project, its purpose, and its goals. A project can contain multiple specifications. To create specifications, you can use existing templates or create a new one. For example, prerequisites and functional specifications.

You can create specifications using existing templates or create a new one. For more information on specification templates, refer to the Creating Templates topic.


To create specifications, follow these steps:

- 1. Go to Application Menu > Data Catalog > Requirements Manager.
- 2. In the **Requirements Workspace** pane, right-click a project.



### 3. Click Create Specification.

The Create Specification page appears.



4. Enter appropriate values to the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field Name                               | Description  |
|--|--|
| Specification<br>Template<br>Type        | Displays a list of available specification templates. Select an appropriate template. You can create templates and add artifacts to templates under <a href="Requirements Manager Settings">Requirements Manager Settings</a> .  For example, Health Migration Template. |
| Specification<br>Template<br>Description | Displays the selected specification template type's description.  For example: The Health Migration Template is to capture functional and business requirements of the data migration project.   |
| Specification<br>Name                    | Specifies the name of the specification.  For example, OrganMatch.  Specifies the version of the specification.  |
| Specification<br>Version                 | For example, 1.01.  Specification version is autopopulated. For more information on specification version, refer to the Configuring Version Display topic.   |
| Version Label                            | Specifies the version label of the specification.  For example, Beta.  For more information on specification version label, refer to the Configuring Version Display topic.  |
| Specification<br>Description             | Specifies the description of the specification.  For example: The specification uses the Health Migration Template to capture functional and business requirements of the data migration project.  |
| Specification<br>Owner                   | Specifies the specification owner's name. For example, Jane Doe.   |
| Status                                   | Specifies the status of the specification.  For example, Pending Review.   |
| Mail Com-<br>ments                       | Specifies mail comments that are sent to project users.  For example: The specification uses the Health Migration Template.  |

| Field Name | Description   |
|------------|---|
|            | For more information on configuring email notifications, refer to the |
|            | Configuring Email Settings topic.                                     |

# 5. Click 🖺 .

A new specification is created and added to the Specifications tree.

A tree of artifacts appears under the specification node. These are the artifacts that were added to the selected specification template.

Once a specification is added to a project, you can enrich it further by:

- Documenting requirements
- Adding supporting documents
- Setting up collaborations
- Creating child artifacts

Right-click a specification in the Requirements Workspace pane to manage it. <u>Managing specifications</u> involves:

- Editing specifications
- Creating specification version
- Sharing specification link
- Exporting and importing specifications
- Copying specifications
- Deleting specifications

### **Documenting Requirements**

Based on the template that you use to create a specification, it contains one or more sections. These sections are called artifacts. You can document your requirements under these artifacts.

To document requirements, follow these steps:

- 1. In the **Requirements Workspace** pane, expand a project.
- 2. Select a specification.

The specification opens in a detailed view. The Specification Overview tab displays specification information and its artifacts. The artifacts available here are based on the template used to create the specification.



- 3. Hover over an artifact title and click .
- 4. Enter requirements in the text area and click \(\begin{align\*}
  \begin{align\*}
  \delta \delt

Additionally, you can add child artifacts to an existing artifact. For more information, refer to the <u>Creating Child Artifacts</u> topic.


### **Adding Supporting Documents**

You can add supporting documents, such as text files, audio files, video files, document links, and so on to a specification.

To add supporting documents, follow these steps:


1. In the **Requirements Workspace** pane, select a specification.

The specification opens in a detailed view.




### 2. Click the **Supporting Documents** tab.

The following page appears.



### 3. Click •

The New Document Form page appears.



4. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field Name                | Description  |
|---------------------------|--|
| Document<br>Name          | Specifies the name of the document being attached to the specification.  |
|                           | For example, Functional Requirements.  |
| Document<br>Object        | Drag and drop document files or click = to select and upload document files.   |
| Document<br>Owner         | Specifies the document owner's name.   |
| Document<br>Link          | Specifies the URL of the document.   |
|                           | For example, https://drive.google.com/file/l/2sC2_SZIyeFKI7OOn-b5YkMBq4ptA7jhg5/view                                 |
|                           | Specifies the description of the document.   |
| Description               | For example: The document contains a detailed record of the functional requirements of the data integration project. |
| Approval<br>Required Flag | Specifies whether the document requires approval.  |
|                           | Select the <b>Approval Required Flag</b> check box to select the document status.                                    |
| Document                  | Specifies the status of the document.  |
| Status                    | For example, In Progress.  |

| Field Name | Description  |
|------------|--|
|            | This field is available only when the Approval Required Flag check box |
|            | is selected.   |

5. Click

The document is added to the Supporting Documents list.

## **Setting up Collaborations**

You can start discussions on specifications or a relevant topic with your team using the Collaboration Center. This enables you and your team to work together.

To set up collaborations, follow these steps:

- 1. In the **Requirements Workspace** pane, select a specification. The specification opens in the detailed view.
- 2. Click the Collaboration Center tab.



3. Click +

The Add Topic page appears.



- 4. Enter Topic Name and Description.
- 5. Click ... The User Assignment page appears.
- 6. Select the users or your team members that you want to collaborate with.
- 7. Click

The topic is saved and added to the list of topics in the Collaboration Center. The topic is also added to the Collaboration Center of the users that you selected earlier.

Once you have created a new topic, you can manage them. <u>Managing collaborations</u> involves:

- Viewing topic details
- Editing topic details
- Assigning users
- Saving conversations as test
- Sending topics in an email
- Deleting topic
- Restoring or purging topics


## **Managing Collaborations**

Managing collaborations involves:

- Viewing topic details
- Editing topic details
- Assigning users
- Saving conversations as test
- Sending topics in an email
- Deleting topic
- Restoring or purging topics

To manage collaborations, follow these steps:

- 1. In the **Requirements Workspace** pane, select a specification. The Specification Overview page appears.
- 2. Click Collaboration Center tab.
- 3. Click



4. Use the following options:

#### **View Topic Details**


Use this option to view the topic and its information, such as the creator, the creation date and time, and the modification date and time.

#### **Edit Topic Details**


Use this option to edit the topic name and description to enrich it further.

### **Assign Users**

Use this option to assign additional users to collaborate with you and contribute to the topic.



Select one or more users and then click . The selected users are assigned to the topic and collaborate with each other.



#### **Save Conversation as Text**

Use this option to save the conversation to a .txt file.

#### **Send Topic as Email**

Use this option to send the topic and its conversations in an email. Clicking Send Topic as Email opens an email recipient list, where you can select one or multiple recipients. Click to send an email to the selected recipients.


#### **Delete Topic**

Use this option to delete the topic. The topic is deleted for all the assigned users.

Note: Any assigned user can delete the topic.

#### **Restore or Purge Topic**

The deleted topic can be restored or deleted permanently (Purge). Click **Restore or Purge Topic**.



To restore the topic, click **Restore** and then, click


To delete the topic permanently, click **Purge** and then, click  $\blacksquare$ .

## **Creating Child Artifacts**

To create better structured specifications and to enrich them further, you can create multiple child artifacts under an artifact.


To create child artifacts, follow these steps:

1. In the Requirements Workspace pane, right-click an artifact.



2. Click New < Artifact\_Name >.

The New Specification Artifact page appears.




3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field<br>Name | Description   |
|---------------|---|
| Name          | Specifies the name of the child artifact.                               |
|               | For example, Enrollments from Healthcare.                               |
| Description   | Specifies the description of the child artifact.                        |
|               | For example: The child artifact captures functional requirements of the |
|               | healthcare department.  |
|               | This field can be disabled while adding the artifact to the template.   |
|               | Specifies the mail comments that are sent to the project users.         |
|               | For example: This child artifact is under the Enrollments artifact.     |
|               | For more information on sending mail comments to project users, refer   |
|               | to the <u>Configuring Email Settings</u> topic.                         |

# 4. Click .

A child artifact is saved and added to the artifact tree. You can view the child artifact on the Specification Overview tab.




# **Managing Specifications**

You can preview the specifications and manage them. Managing specifications involves:

- Editing specifications
- Creating specification version
- Sharing specification link
- Exporting and importing specifications
- Copying specifications
- Deleting specifications

To manage specifications, follow these steps:

1. Right-click a specification to view specification management options.



2. Use the following options:

**New Version** 

Use this option to create specification versions. You can maintain one working version and archive older versions for reference. For more information, refer to the <a href="Maintain"><u>Creating</u></a> Specification Version topic.

#### **Specification Preview**

Use this option to preview the specification.

#### **Share Link**


Use this option to generate a sharable specification URL. You can copy the URL to share or send the URL through an email using an email client.

#### **Export Specification**

Use this option to download a specification in .xml format. You can use the downloaded specification to import it to another project. For more information, refer to the Exporting and Importing Specifications topic.

#### **Copy Specification**


Use this option to copy specifications.



Use one of the following options:

- **Copy Selected**: Use this option to copy the selected specifications.
- **Copy All**: Use this option to copy the specification and its archived versions.

After copying specifications, you can paste them in a project.



**Delete Specification** 

Use this option to delete specifications. You can also delete all the versions of the specification using this option.

#### **Edit Specifications**

Use this option to edit the specification. To edit specification, select a specification and click . Then, update the specification and save the changes.

- Click the **Specifications** node.
   The specification Listing pager appears.
- 2. Click . The Specification Details page appears in edit mode.
- 3. Update the required fields and click .


  The specification is updated.

### **Creating Specification Versions**

You can create versions of a specification, and maintain one working version and archive the older versions for reference. You can also compare any two versions of the specifications to view differences.


To create specification versions, follow these steps:

1. In the **Requirements Workspace** pane, right-click the required specification.



#### 2. Click New Version.

The New Version page appears.



3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field Name    | Description  |
|---------------|--|
| Specification | Specifies the name of the specification.                               |
| Name          | For example, OrganMatch.   |
| Specification | Specifies the new version of the specification.                        |
| Version       | For example, 1.02.   |
|               | Specifies the version label of the specification.                      |
| Version       | For example, Beta.   |
| Label         | For more information on configuring version display of specifications, |
|               | refer to the Configuring Version Display of Specifications topic.      |
| Change        | Specifies the description of the changes made in the specifications.   |
| Description   | For example: A new child artifact was added to the specification tem-  |

| Field Name         | Description   |
|--------------------|---|
|                    | plate.  |
| Mail Com-<br>ments | Specifies the mail comments which are sent to the project users.                    |
|                    | For example: The new version of the specification contains one more child artifact. |
|                    | For more information on sending mail comments to project users, refer               |
|                    | to the Configuring Email Settings topic.  |


## 4. Click

A version of the specification is created and added to the Specifications tree.

The older specification version is archived and cannot be edited.

To compare the two versions of a specification, follow these steps:


- 1. In the **Requirements Workspace** pane, use the CTRL key to select the two versions that you want to compare.
- 2. Right-click the selected specification.



#### 3. Click Compare Specification.

The Specification Comparison Report appears. This report displays a comparison of two specifications.

For example, the differences are highlighted in red color and unchanged details are displayed in black color. See the below image for more information.



# **Exporting and Importing Specifications**

You can export specifications in .xml format and import them to the a same or different project.


To export specifications, follow these steps:

1. In the **Requirements Workspace** pane, right-click the required specification.



#### 2. Click Export Specification.

The Download File hyperlink appears in the notification area.



#### 3. Click Download File.

The specification is downloaded as a .zip file.

You can create a specification by importing the exported specification.


To import a specification, follow these steps:

1. Unzip the exported specification.

The unzipped folder contains the exported specification in the .xml format.


**Note**: If you are importing the specification to the same project, then change the Specification Name and the Template Name in the .xml file. If you are importing the specification to a different project, you can import the .xml file as it is.

- 2. Go to Application Menu > Data Catalog > Requirements Manager.
- 3. In the Requirements Manager pane. right-click a project.



4. Click Import Specification.

5. Drag and drop the .xml file or use = to browse the file.



6. Click 1.

The specification is created and added to the Specifications tree.


# **Linking Requirements to Data Mappings**

To ensure enterprise-wide traceability, you can link your functional requirements to data mappings.

To link functional requirements to mappings, follow these steps:


- 1. Go to Application Menu > Data Catalog > Mapping Manager.
- 2. Click a mapping.

The mapping opens in the detailed view.



3. On the **Mapping Specification** tab, right click the grid header.

A list of header columns appears.




4. Scroll down the list and select the s**Specification Artifact** check box.

The specification Artifact column becomes visible on the Mapping Specification tab.

- 5. In the right pane, click Specification Artifact Catalogue.
- 6. Expand the project that contains the required specification.

7. Drag and drop the specification on the **Specification Artifacts** column in the required row.



8. Click .


Requirements are linked to the selected mapping.

# **Using Test Manager**

The Test Manager enables you to view and analyze test cases across projects and metadata levels. It provides a dashboard with the project and test cases statistics that help you manage your test cases.

To access the Test Manager, go to **Application Menu > Data Catalog > Test Manager**.

The Test Manager dashboard appears:



| UI Section  | Function  |
|-------------|---|
| 1-Test Pro- | Use this pane to browse through test cases created in the Metadata Manager            |
| jects       | and the Mapping Manager. Test cases are listed under projects.                        |
| 2-Right     | Use this pane to view project and test case statistics, and test case status for pro- |
| Pane        | jects.  |
| 3-Project   | Based on your selection in the Test Projects pane, use this pane to view a list of    |
| Summary     | projects or test cases.   |

Once you have created test cases in the Mapping Manager and Metadata Manager, you can view and analyze them in the Test Manager.

# **Creating and Managing Test Cases**

You can create, edit, and clone the test cases for project maps, tables, ETL processes: then define actual and expected results. You can also import and export test cases in the XLS format.

For more information on creating test cases, refer to the following topics:


- Creating and Managing Test Cases for Mappings
- Creating and Managing Test Cases for Tables

# **Viewing and Analyzing Test Cases**

You can view and analyze all the test cases created in the Mapping Manager and Metadata Manager at one place in the Test Manager.

To view and analyze test cases, follow these steps:

1. Go to Application Menu > Data Catalog > Test Manager.



The following information about the selected project is displayed in the right pane.

#### **Project Statistics**

Use this section to view the following information:

**Projects**: It displays the number of projects in the Test Manager.

**Mappings**: It displays the number of mappings with at least one map-level test case.

**Tables**: It displays the number of tables with at least one metadata-level test case.

**Test Cases**: It displays the count of total number of test cases in the Mapping Manager and Metadata Manager.

**Test Steps**: It displays the total count of validation steps in all the test cases.

#### **Project Test Case Status**

Use this section to view the test case statuses in a pie chart. The test case status can be:

- Passed
- Failed
- Unspecified
- Need Analysis
- No Run
- Design


### **Project Summary**

Use this section to displays the list of projects The Project names follow a nomenclature:

- Projects containing metadata level test cases follow, <System Name>\_
   <Environment Name>
- Projects containing project level test cases and map level test cases have the same name as that of the project in the Mapping Manager

The metadata-level test cases are created in the Metadata Manager. The project-level and map-level test cases are created in the Mapping Manager.


2. In the Test Projects pane, click a project.



**Test Case Statistics, Test Case Status,** and **Test Case Summary** are displayed in the right pane.

3. Click a test case to view its details.

The test case opens in a detailed view.



Work on the following tabs to view and analyze the test cases:

#### **Test Case Overview**

Use this tab to view the test case details.


#### **Validation Steps**

Use this tab to view the validation steps in the test case.

### **Document Upload**


Use this tab to view the uploaded documents in the test case.

Expand My Test Cases node to browse the test cases you (logged in user) created.



# **Using Release Manager**

To access the Release Manager, go to **Application Menu** > **Data Catalog** > **Release Manager**. The Release Manager dashboard appears:



| UI Section | Function  |
|------------|---|
| 1-Browser  | Use this pane to browse through releases and miscellaneous options. |
| Pane       | You can switch between different views to see releases:             |

|          | Calendar View: Select this view to list the releases on a calendar                     |
|----------|--|
|          | <ul><li>Project View: Select this view to list the releases under a project.</li></ul> |
|          | • Release View: Select this view to list release object details under a release.       |
| 2-Bottom | Use this pane to view or work on the data based on your selection in the               |
| Pane     | browser pane.  |

Managing releases involve the following:


- Creating projects and adding releases
- Adding release objects to releases
- Moving release objects
- Sorting projects and releases

# **Creating Projects and Adding Releases**

You can create projects and add releases to these projects.


To create projects, follow these steps:

1. In the Release Manager page, click the **Project View** tab.



2. Click Add Project.

The New Project page appears.



3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field Name           | Description  |
|----------------------|--|
| Droject Name         | Specifies the name of the project.                         |
| Project Name         | For example, EDW.  |
| Project Description  | Specifies the description about the project.               |
| Project Description  | For example: List of releases targeted this spring.        |
| Resource Name        | Specifies the project owner's name.                        |
|                      | For example, Jane Doe.                                     |
|                      | Specifies the description about the project owner.         |
| Resource Description | For example: Jane Doe is the release manager of the organ- |
|                      | ization.   |
| Resource Cell Phone  | Specifies the cell phone number of the project owner.      |
|                      | For example, +658374414288.                                |
| Resource Work        | Specifies the work phone number of the project owner.      |

| Field Name     | Description                                  |
|----------------|--|
| Phone          | For example, 1-800-783-7946.                 |
| Resource Email | Specifies the project owner's email address. |
|                | For example, jane.doe@mauris.edu             |

#### 4. Click Save.


The project is created and saved in the Project Listing.

To add releases to the project, follow these steps:

1. Under the **Project Listing** section, select a project.


The Release Listing for the project appears under the Release Listing for: section.

If there are not release associated to a project, the list will be empty.



#### 2. Click Add Release.

The New Release page appears.




3. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field Name             | Description  |
|------------------------|--|
| Project                | Specifies the project name for a release.                                    |
| Name                   | For example, EDW.  |
| Release                | Specifies the name of the release.   |
| Name                   | For example, Pfizer Test.  |
| Poloaco                | Specifies the description about the release.                                 |
| Release<br>Description | For example: The release contains two release objects of the data item type. |
| Change Con-            | Specifies the change control number of the release.                          |
| trol Number            | For example, v1.8.   |
|                        | Specifies the date of the release.   |
| Release<br>Date        | For example, 01/22/2020.   |
|                        | Use to enter the release date.   |
| Release                | Specifies the release owner's User ID.                                       |
| Owner                  | For example, jdoe.   |

| Field Name    | Description   |
|---------------|---|
|               | This list displays the users available in the Resource Manager. For more    |
|               | information on creating users, refer to Creating Users and Assigning        |
|               | Roles.  |
| User          | Specifies the III label name of additional You can define the III labels in |
| Detined       | Specifies the UI label name of additional. You can define the UI labels in  |
| Fields (1-10) | the Language Settings.  |

#### 4. Click Save.

The release is added to the selected project.



## 5. Use the following options:

## View (©)

To view the release details, click .

## Edit (🖍)

To edit, the release, click ...

You can update the release status only by editing a release.

## Download (₺)

To download the release details, click ₹.

#### Delete (X)

To delete the release, click X.

Once a release is created, you can add release objects to it.

# **Adding Release Objects to Releases**

You can add following release objects to releases:

- Data item mappings
- Codesets
- Code mappings
- Miscellaneous objects


**Note**: You can add new release object types under the Miscellaneous Objects list in the Release Manager Settings.

## **Adding Data Item Mappings as Release Objects**

Data item mappings can be added as release objects to a release. While adding a data item mapping, ensure that the mapping is not in edit mode (locked state).

To add data item mappings as release objects to a release, follow these steps:

Under the **Project View** tab, in the **Project Listing** section click the required project.
 The release listing of the project appears.




2. Click the required <Release\_Name>.

The Release View page appears showing the release object details.


3. Click Add Object.

The Migration Object Entry Form page appears.




4. In Select Object Types, select Add Data Item Mapping.

The following page appears.



5. Select the required mappings and click **Next**.

The Migration Object Entry Form page reappears.



6. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field<br>Name | Description  |
|---------------|--|
|               | Specifies the description about the release object being added to the    |
| Object        | release.   |
| Description   | For example: The release object is a data item mapping under the Dat-    |
|               | awarehouse project.  |
|               | Specifies the live date and time of the release object.                  |
| Live Date /   | For example, 04/03/2020 9:30 AM.   |
| Time          | Live Date is autopopulated and it is same as the release date.           |
|               | Enter the Live Time in HH : MM format.                                   |
| Migration     | Specifies the migration date and time of the release object from the DEV |

| Field<br>Name  | Description   |
|----------------|---|
|                | release environment.  |
|                | For example, 04/30/2020 9:30 PM.  |
| Date /<br>Time | Use I to enter the migration date. Enter the migration time in the HH: MM format.   |
|                | The Migration Date cannot exceed the Live Date.   |
| Migration      | Specifies the current release environment of the release object.  |
| From           | This field is set to DEV by default.  |
| DCN            | Specifies the DSN name from where the release object is being migrated.   |
| DSN            | For example, ErwinDIS931.   |
| IP Address     | Specifies the IP Address from where the release object is being migrated.   |
| IP Address     | For example, 10.32.445.21   |
| Migration      | This field is set to DEV by default. You can use the Promote Map option to  |
| To             | migrate the selected data item mappings to the required release envir-  |
|                | onment for the first time.  |
| DSN            | Specifies the DSN name to which the release object is being migrated.   |
| DSIN           | For example, ErwinDIS932.   |
| IP Address     | Specifies the IP address to which the release object is being migrated.   |
| IP Address     | For example, 10.31.447.22   |
|                | Specifies the User ID of the release object's owner.  |
| Owner /        | For example, jdoe.  |
| Assignee       | The option list appears based on the users created in the Resource Manager. For more information on creating users, refer to the Creating Users |
|                | and Assigning Roles topic.  |

## 7. Click **Save**.

The data item mappings are added as release objects to the release.



### 8. Use the following options:

## Edit (🖍)

To edit the release object, click .

You can update the release object status only by editing a release object.

**Note**: Use Edit option to migrate the data item mappings to a release environment for the second time and subsequently.

# Information (10)

To view the mapping information, click  $oldsymbol{0}$ .

## Download (₺)

To download the release object details, click **₹**.

#### Email (≥)

To send email notification about the release object click ...

#### Delete (x)

To delete the release object, click X.

## **Promoting Data Item Mappings**


You can promote data item mappings to different release environments in the Release Manager.

The promotion is reflected in the Mapping Manager and hence, it is important to assign promote system environments (for source and target) corresponding to the release environments.

To promote data item mappings, follow these steps:


1. Under the Project View tab, click the required project.

The release listing of the project appears.




2. Click the required <Release\_Name>.

The Release View tab appears.



3. In the **Release Object Details** section, click the required <Data\_Item\_Mapping\_ Object> and click **Promote Maps**.

The Promote Data Item Mappings page appears.




4. In **Data Item Repository**, select the required **<Map\_Name>** check box.

5. In **Promotion Details**, enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.


| Field Name        | Description   |
|-------------------|---|
| Promote To        | Specifies the release environment to which the release object is being promoted.                        |
|                   | For example, TEST.  |
|                   | Select the <u>release environment</u> where you wish to promote the release object (data item mapping). |
|                   | Specifies the effective migration date of the release object.   |
| Effective<br>Date | For example, 04/22/2020.  |
| Date              | Use 🔙 to enter the effective migration date.  |
| Version           | Specifies the version label of the release objects.   |
| Label             | For example, Beta.  |
|                   | Specifies the notes about the publishing of the data item mapping.                                      |
| Publish Notes     | For example: The data item mappings should be promoted to the Adven-                                    |
|                   | tureworks_Migration.  |
| Change            | Specifies the description about the changes in the data item mapping.                                   |
| Description       | For example: The business rule in the data item mappings was changed to ABORT.                          |
| Publish To        | Specifies the project in the Mapping Manager to which the data item                                     |
| Project           | mapping is being promoted.  |
|                   | For example, Adventureworks_Migration.  |
| Publish To        | Specifies the Subject Area in the Mapping Manager to which the data                                     |
| Subject           | item mapping is being promoted.   |
|                   | For example, Providers.   |

## 6. Click Validate.

The Promotion Error Report appears, because corresponding promote system environments were not provided.




7. Double-click the corresponding cells to select the promote system environment for the mappings.




8. Click Save.

The promote system environments are assigned.



### 9. Click Validate.

The promotion is successfully validated.



## 10. Click Promote.

The object is promoted to the selected project.

**Note**: When the data item mapping object is promoted, then it moves to the specified project in the Mapping Manager. The source and the target environment are also modified to the specified promote system environments.


# **Adding Codeset as Release Objects**

You can add codesets as release objects to a release and specify migration environment and date.

To add codesets as release objects to a release, follow these steps:

1. Under the Project View tab, click the required project.

The release listing of the required project appears.




2. Click the required <Release\_Name>.

The Release View page appears.


3. Click Add Object.

The Migration Object Entry Form page appears.




## 4. In Select Object Types, select Add Codeset.

The following page appears.



5. Select the required codesets and click Next.

The Migration Object Entry Form page reappears.



6. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.


| Field<br>Name     | Description   |
|-------------------|---|
| o sjece           | Specifies the description about the release object being added to the release.          |
|                   | For example: The release object is a codeset under the 3rd Party Flat Files category.   |
|                   | Specifies the live date and time of the release object.                                 |
| Live Date /       | For example, 04/03/2020 9:30 AM.  |
| Time              | Live Date is autopopulated and it is same as the release date.                          |
|                   | Enter the Live Time in HH : MM format.  |
|                   | Specifies the migration date and time of the release object from a release environment. |
| Migration         | For example, 04/30/2020 9:30 PM.  |
| Date /<br>Time    | Use <b>to enter the migration date.</b> Enter the migration time in the HH: MM format.  |
|                   | The Migration Date cannot exceed the Live Date.   |
|                   | Specifies the current release environment of the release object.                        |
| Migration<br>From | For example, DEV.   |
| 110111            | You can create release environments in the Release Manager Settings.                    |
| DSN               | Specifies the DSN name from where the release object is being migrated.                 |
| DSIN              | For example, ErwinDIS931.   |
| IP Address        | Specifies the IP Address from where the release object is being migrated.               |
| II Addi C33       | For example, 10.32.445.21   |
|                   | Specifies the release environment to which the release object is being                  |
| Migration<br>To   | migrated.   |
|                   | For example, TEST.  |
|                   | You can create release environments in the Release Manager Settings.                    |
| DSN               | Specifies the DSN name to which the release object is being migrated.                   |
|                   | For example, ErwinDIS932.   |
| IP Address        | Specifies the IP address to which the release object is being migrated.                 |

| Field<br>Name       | Description   |
|---------------------|---|
|                     | For example, 10.31.447.22   |
| Owner /<br>Assignee | Specifies the User ID of the release object's owner.                      |
|                     | For example, jdoe.  |
|                     | The option list appears based on the users created in the Resource Man-   |
|                     | ager. For more information on creating users, refer to the Creating Users |
|                     | and Assigning Roles topic.  |

#### 7. Click Save.

The selected codesets are added as release objects to the release.

**Note**: Object Status can be modified by editing the release object. You can add or remove a release object status in the Release Manager Settings.



## 8. Use the following options:

# Edit (🖍)

To edit, the release object, click .

You can update the release object status only by editing a release object.

Information (10)

To view the mapping information, click lacktriangle.

## Download (₺)

To download the release object details, click **\L**.

### Email (≥)

To send email notification about the release object click **■**.

#### Delete (x)

To delete the release object, click \*.


# **Adding Code Mappings as Release Objects**

You can add code mappings as release objects to a release and specify migration environment and date.

To add code mappings as release objects to a release, follow these steps:

1. Under the **Project View** tab, click the required project.

The release listing of the required project appears.




2. Click the required <Release\_Name>.

The Release View page appears showing the release object details.


3. Click Add Object.

The Migration Object Entry Form page appears.




4. In Select Object Types, select Add Code Mappings.

The following page appears.



5. Select the required code mappings and click **Next**.

The Migration Object Entry Form page reappears.




6. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.

| Field<br>Name         | Description   |
|-----------------------|---|
| Object<br>Description | Specifies the description about the release object being added to the release.          |
|                       | For example: The release object is a code map under the EDW category.                   |
|                       | Specifies the live date and time of the release object.                                 |
| Live Date /           | For example, 04/03/2020 9:30 AM.  |
| Time                  | Live Date is autopopulated and it is same as the release date.                          |
|                       | Enter the Live Time in HH : MM format.  |
|                       | Specifies the migration date and time of the release object from a release environment. |
| Migration             | For example, 04/30/2020 9:30 PM.  |
| Date /<br>Time        | Use <b>to enter the migration date.</b> Enter the migration time in the HH: MM format.  |
|                       | The Migration Date cannot exceed the Live Date.   |
|                       | Specifies the current release environment of the release object.                        |
| Migration<br>From     | For example, DEV.   |
| 110111                | You can create release environments in the Release Manager Settings.                    |
| DCN                   | Specifies the DSN name from where the release object is being migrated.                 |
| DSN                   | For example, ErwinDIS931.   |
| IP Address            | Specifies the IP Address from where the release object is being migrated.               |
| Address               | For example, 10.32.445.21   |
|                       | Specifies the release environment to which the release object is being                  |
| Migration             | migrated.   |
| То                    | For example, TEST.  |
|                       | You can create release environments in the Release Manager Settings.                    |
| DSN                   | Specifies the DSN name to which the release object is being migrated.                   |
|                       | For example, ErwinDIS932.   |
| IP Address            | Specifies the IP address to which the release object is being migrated.                 |
|                       | For example, 10.31.447.22   |

| Field<br>Name       | Description  |
|---------------------|--|
| Owner /<br>Assignee | Specifies the User ID of the release object's owner.   |
|                     | For example, jdoe.   |
|                     | The option list appears based on the users created in the Resource Man-  |
|                     | ager. For more information on creating users, refer to the <u>Creating Users</u> and <u>Assigning Roles</u> topic. |

#### 7. Click Save.

The selected code mappings are added as release objects to the release.



### 8. Use the following options:

## Edit (🖍)

To edit, the release object, click .

You can update the release object status only by editing a release object.

# Information (10)

To view the mapping information, click ①.

## Download (₺)

To download the release object details, click **\L**.

### Email (≥)

To send email notification about the release object click ...

### Delete (x)

To delete the release object, click .


# **Adding Miscellaneous Objects**

You can create your own release object types under the miscellaneous objects in the Release Manager Settings and add those type of release objects to a release in the Release Manager. For more information on adding miscellaneous object types, refer to the <u>Configuring Release Object Types</u> topic.

To add miscellaneous objects to a release, follow these steps:

1. Under the Project View tab, click the required project.

The release listing of the required project appears.




2. Click the required <Release Name>.

The Release View page appears.

### 3. Click Add Object.

The Migration Object Entry Form page appears.



- 4. In Select Object Types, select Add Miscellaneous Objects.
- 5. Enter appropriate values in the fields. Fields marked with a red asterisk are mandatory. Refer to the following table for field descriptions.


| Field<br>Name         | Description  |
|-----------------------|--|
| Object                | Specifies the name of the release object being added to the release.                 |
| Name                  | For example, AdventureWorks_DDL.   |
| Object<br>Description | Specifies the description about the release object.                                  |
|                       | For example: The release object is the DDL script of the AdventureWorks environment. |
| Object                | Specifies the release object type.   |

| Field<br>Name     | Description   |
|-------------------|---|
| Туре              | For example, DDL Script.  |
|                   | You can <u>add object type</u> in the Release Manager Settings.                         |
| Choose File       | Specifies the physical file being attached to the release object.                       |
| CHOOSE FILE       | Click <b>Browse</b> to select the file.   |
|                   | Specifies the live date and time of the release object.                                 |
| Live Date /       | For example, 04/03/2020 9:30 AM.  |
| Time              | Live Date is autopopulated and it is same as the release date.                          |
|                   | Enter the Live Time in HH : MM format.  |
|                   | Specifies the migration date and time of the release object from a release environment. |
| Migration         | For example, 04/30/2020 9:30 PM.  |
| Date /<br>Time    | Use I to enter the migration date. Enter the migration time in the HH: MM format.       |
|                   | The Migration Date cannot exceed the Live Date.   |
| NA:ti             | Specifies the current release environment of the release object.                        |
| Migration<br>From | For example, DEV.   |
| 110111            | You can create release environments in the Release Manager Settings.                    |
| DSN               | Specifies the DSN name from where the release object is being migrated.                 |
| אוכטו             | For example, ErwinDIS931.   |
| IP Address        | Specifies the IP Address from where the release object is being migrated.               |
|                   | For example, 10.32.445.21   |
|                   | Specifies the release environment to which the release object is being                  |
| Migration<br>To   | migrated.   |
|                   | For example, TEST.  |
|                   | You can create release environments in the Release Manager Settings.                    |
| DSN               | Specifies the DSN name to which the release object is being migrated.                   |
|                   | For example, ErwinDIS932.   |
| IP Address        | Specifies the IP address to which the release object is being migrated.                 |

| Field<br>Name       | Description   |
|---------------------|---|
|                     | For example, 10.31.447.22   |
| Owner /<br>Assignee | Specifies the User ID of the release object's owner.                      |
|                     | For example, jdoe.  |
|                     | The option list appears based on the users created in the Resource Man-   |
|                     | ager. For more information on creating users, refer to the Creating Users |
|                     | and Assigning Roles topic.  |

#### 6. Click Save.

The release object is added to the release.



## 7. Use the following options:

# Edit (🖍)

To edit, the release object, click 🖍.

You can update the release object status only by editing a release object.

# Information (10)

To view the mapping information, click ①.

## Download (₺)

To download the release object details, click **±**.

### Email (≥)

To send email notification about the release object click ...

## Delete (**≭**)

To delete the release object, click x.

# **Moving Release Objects**


You can move release objects to a different release within the same project or to a release in a different project.

Note: You cannot move a data item mapping object.

To move release objects, follow these steps:


1. Under the Project View tab, click the required project.

The release listing of the required project appears.




Click the required <Release Name>.

The Release View page appears showing the release object details.



3. Click Move Object.

The Move Object page appears showing the Release Objects Data Repository.



4. In the Release Objects Data Repository tab, select the release objects.

- 5. In the **Move To** tab, Select the project and the release where the release objects should move to.
- 6. Click Save.

The release object moves to the selected project and the selected release.


## **Sorting Projects and Releases**

You can sort project listing in the Project View by:

- a. Project Name
- b. Owner
- c. Created Date
- d. Last Modified Date

To sort projects, follow these steps:

1. Go to Application Menu > Data Catalog > Release Manager > Miscellaneous.



2. Click Settings.

The following page appears.



- 3. Click .
- 4. Select the appropriate **Project Sorting By** option.
- 5. Select the appropriate **Sorting On** option.
- 6. Click Save.


The project listings are sorted in the Project View.

You can sort release listings by:

- a. Release Name
- b. Owner
- c. Release Status
- d. Release Date
- e. Created Date
- f. Last Modified Date

To sort release listings, follow these steps:

1. Go to Application Menu > Data Catalog > Release Manager > Miscellaneous > Settings.



- 2. Click .
- 3. Select the appropriate Release Sorting By option.
- 4. Select the appropriate **Sorting On** option.
- 5. Click Save.

The release listings are sorted in the Project View.